

PDF-4+/Web 2022

PDF-4+/Web 2022 is licensed for use on a PC that has the PDF-4+/Web hardware dongle attached. The software may be installed on any number of computers; however, the licensed software can only be operated on the computer with the dongle attached. For concurrent access to the PDF-4+/Web database, additional licensed dongles must be purchased. Each dongle must be registered to enable a connection to the ICDD database server.

The PDF-4+/Web 2022 database contains integrated data mining software and ICDD's search-indexing software, Sleve+ (sold separately). In order for Sleve+ to be activated, a license for Sleve+ must be purchased from ICDD or your vendor. **The full license period is for one year following the date of registration.**

OEM and Vendor Software

Please contact your software vendor to determine its compatibility with PDF-4+/Web 2022. Several OEM and vendor software packages support PDF-4+/Web 2022. In addition, some software vendors provide the ability to save their compiled index files to the dongle's flash memory facilitating portability between computers.

Caution: A fee of \$500 USD will be charged to replace lost dongles. In order to receive a replacement dongle, you need to report the lost dongle's serial number to sales@icdd.com. ICDD will "turn-off" the lost dongle and ship a replacement dongle upon verification of your license.

Licensing

Please carefully review the PDF-4+/Web 2022 license.

Windows® 7 SP1 users: Click Start > All Programs > ICDD PDF-4+ Web 2022 > Read License.txt.

Windows® 8/8.1 users: Press the Windows® logo key for the "Start" screen, then click the tile labeled Lic-PDF-4+ Web 2022.

Windows® 10 users: Click Start > All apps > ICDD PDF-4+ Web 2022 > Read License.txt.

Installation

Your computer must satisfy the System Requirements in this document before continuing.

1. Get the latest installation file, PDF-4+ Web 2022.exe.
 - New user: The latest installation is on your USB dongle.
 - Renewing customer: Download from <https://webpdf4.icdd.com/2022/downloads/>.
2. Close all running programs.
3. Run the installation with **Administrator** privileges and follow the on-screen instructions.
4. Activate your license for 2022.
 - a. Insert the PDF-4+/Web USB dongle.
Renewing customer will use his/her existing PDF-4+/Web USB dongle.

- b. Determine your operating system to register your PDF-4+/Web product directly at <https://webpdf4.icdd.com/2022/registration/login.htm>.
 - Windows 7 users: Click Start > All Programs > ICDD PDF-4+/Web 2022 > “Register ICDD Product”
 - Windows® 8/8.1 users: Press the Windows® logo key for the "Start" screen, and then click the tile labeled "Register-PDF-4+ Web 2022".
 - Windows® 10 users: Click Start > All apps > ICDD PDF-4+ Web 2022 > Register ICDD Product.
- c. You will receive an email confirmation once the product is successfully registered.

Running the Software

TCP/IP ports 3333 and 22222 must be open—see FAQ #2 and #3.

1. Insert the PDF-4+/Web USB dongle.
2. Launch the PDF-4+/Web 2022 using any account with **User** privileges.
 - Use the Desktop shortcut “PDF-4+ Web 2022” or Windows® 10 users: Click Start > All apps > ICDD PDF-4+ Web 2022 > “ICDD PDF-4+ Web 2022”.

Stopping the Software

1. Exit the PDF-4+/Web 2022 software.
2. Close the ICDD Communicator.
 - a. When closing the PDF-4+/Web software, you will be asked to close the ICDD Communicator. Select **Yes**.
 - or
 - b. Close the ICDD Communicator by right-clicking on the ICDD Communicator icon in the System Tray (lower right screen) and selecting “**Exit**”.
3. Eject the USB dongle by right-clicking on the turquoise CodeMeter icon in the System Tray and selecting “**Eject all CmSticks**”.
4. Remove the PDF-4+/Web USB dongle.

System Requirements

Hardware:

Intel® Core™ 2 Duo processor or better
4 GB of system memory
NTFS file system
Fully-powered USB port
500 MB free hard drive space
1024 X 768 minimum screen resolution

Supported Operating Systems:

Windows® 7 SP1
Windows® 8
Windows® 8.1
Windows® 10

Operating System Account Permissions:

Installation requires **Administrator** privileges.
Running ICDD software requires **User** privileges.

Internet Access:

Bandwidth: Minimum = 10 Mbps Preferred = 50 Mbps or faster

TCP/IP Ports: 3332 and 22221

TCP/IP ports require outbound access through all firewalls.

RETURN POLICY

Products may be returned within 30 days from the invoice date for a full refund or credit (excluding shipping/handling). Please visit <https://www.icdd.com/ordering/> for further information. **Registered products do not qualify.**

HELP DOCUMENTATION & TUTORIALS

Explore the capabilities of PDF-4+/Web 2022 with our extensive Help documentation, online tutorials and videos. The Help files include a Table of Contents and fundamental information on how to use the database. The online tutorials are designed to demonstrate the features, applications, hints and shortcuts for your PDF-4+ product. Please <https://www.icdd.com/product-tutorials/>.

SUPPORT

www.icdd.com/support

Phone: 610.325.9814 • Toll-free in U.S.A. & Canada: 866.378.9331

Fax: 610.325.9823

Technical Support: support@icdd.com

Registration Support: registration@icdd.com

PDF-4+/Web 2022 contains integrated data mining software and ICDD's search-indexing software, Sleve+. A license for Sleve+ must be purchased from ICDD or your vendor in order for Sleve+ to be activated for the full license period.

**International Centre for Diffraction Data
12 Campus Boulevard
Newtown Square, PA 19073-3273 USA
info@icdd.com
www.icdd.com • www.dxcicdd.com**



ICDD, the ICDD logo and PDF are registered in the U.S. Patent and Trademark Office.
Sleve+ is a trademark of JCPDS—International Centre for Diffraction Data.